



MINIMET


PROBLEM: Off-Load Logs and Summary Reports are blank

If the Off-Load Logs and Summary Reports appear as a blank page only, then your PC or laptop has no printer installed. As these pages are shown as a 'Print Preview' then it is necessary for a printer driver to be installed to display the information on the screen. It is not necessary for an actual printer to be connected to the PC, only a printer driver.

To install a printer driver, go to the Printers folder (depending on the Windows version you are using, go to Start, Settings and Printers). Double click on the Add Printer or Add New Printer icon and proceed through the Wizard.

Choose the Local printer option, but do not tick the 'Automatically detect printer' box if you do not have a printer connected. Choose a printer port, typically LPT1. If you do not have a printer to connect, then choose any printer listed, e.g. HP and HP2000C. Continue through the Wizard to set up this printer.

Now restart the PC and then return to SkyeLynx Auto. The Off-Load Logs should now be showing on screen.



SKYE INSTRUMENTS LTD
21, Ddole Enterprise Park, Llandrindod Wells, Powys, LD1 6DF, UK
Tel: +44(0)1597 824811 Fax: +44(0)1597 824812
Email: skyeemail@skyeinstruments.com Web: www.skyeinstruments.com

