



# MINIMET

## Display Data Summaries


### DISPLAY SUMMARY ON SCREEN

1. Download data from the datalogger as usual
2. Click DATA
3. Click DATA SUMMARIES
3. Click SELECT DATES
4. Choose the date and time to summarise from the START and END calendars
5. Click DONE and then click CONFIRM.
6. Choose the number of days for each summary table, e.g. 1 for a daily summary, 7 for weekly, 31 for monthly etc. Click OK.
7. Click OK to confirm the DataFile Identifier of your DataHog logger

If an error message appears, please see WizzCom FAQs for hints.

### PRINT SUMMARY

1. Click the PRINT button at the bottom of the screen. The data summaries currently being displayed will print to the device currently set as default in Windows.
2. Click CANCEL at the bottom to exit the Data Summaries window.



**SKYE INSTRUMENTS LTD**  
21, Ddole Enterprise Park, Llandrindod Wells, Powys, LD1 6DF, UK  
Tel: +44(0)1597 824811 Fax: +44(0)1597 824812  
Email: [skyemail@skyeinstruments.com](mailto:skyemail@skyeinstruments.com) Web: [www.skyeinstruments.com](http://www.skyeinstruments.com)

