



MINIMET

Choosing WizzCom or SkyeLynx Deluxe software

WizzCom is the predecessor to SkyeLynx Deluxe, although is still fully functioning, Y2K compatible etc. The main differences are:

1. WizzCom hold the logger configuration for just 1 logger, Deluxe holds configurations for up to 25 different loggers.
2. WizzCom stores telephone numbers for up to 10 different GSM remote modem, Deluxe stores up to 25
3. WizzCom will draw a graph from 1 sensor per graph, Deluxe can have up to 10 lines (or 10 sensors) per graph
4. WizzCom has a very simple compass graph for wind direction, Deluxe has a full wind speed & direction WindRose on one graph
5. WizzCom data summary tables (max / min / mean etc) do not give accurate mean calculations for wind direction, Deluxe does give an accurate vectorial mode 'average' or mean value.
6. Deluxe has a more modern looking 'Windows' type menu structure and has a few more automated logger functions

